


# Working with Windows Programs

## Files You Will Need:

WIN B-1.rtf  
WIN B-2.bmp  
WIN B-3.wmv  
WIN B-4.wma  
WIN B-5.wmv  
WIN B-6.wmv  
WIN B-7.rtf  
WIN B-8.bmp  
WIN B-9.rtf  
WIN B-10.bmp  
WIN B-11.wmv  
WIN B-12.wmv

Now that you know how to work with common Windows graphical elements, you're ready to work with programs. A **program** is software you use to accomplish specific tasks, such as word processing and managing files on your computer. Windows comes with several **accessories**—built-in programs that, although not as feature-rich as many programs sold separately, are extremely useful for completing basic tasks. In this unit, you work with some of these accessories.



 You're a tour developer for Quest Specialty Travel, a growing company that uses Windows 7 on its computers. You want to prepare a document outlining ideas for travel packages, so you plan to use two Windows accessories, WordPad and Paint, to create it. You also want to use two other multimedia accessories, Windows Media Player and Windows Media Center, to play travel videos and sound clips and to create a travel movie.

## OBJECTIVES

- Start a program
- Open and save a WordPad document
- Modify text in WordPad
- Work with a graphic in Paint
- Copy data between programs
- Embed or link an object
- Print a document
- Play a video or audio clip
- Work with Windows media



# Starting a Program

A **Windows program** is software designed to run on computers using the Windows operating system. The most common way to start a Windows program is to use the Start menu, which provides easy access to programs installed on your computer. Clicking the Start button  on the taskbar displays the Start menu, which lists common and recently used programs, and the All Programs submenu, which you can click to list all the programs installed on your computer. In this lesson, you start a Windows accessory called **WordPad**, a word-processing program that comes with Windows. A **word processor** is a program that you use to enter, edit, and format text and graphics. As you look for WordPad on the All Programs submenu under Accessories, you might notice an accessory called **Notepad**. The accessory names are similar, and both programs work with text. Notepad is a **text editor**, in which you can enter and edit text only with basic document formatting. With both programs, you can open only one document per open program window at a time.  Before you can use WordPad to prepare a text document of your package ideas, you need to start the program.

## STEPS

### 1. Click the **Start button** on the taskbar

The Start menu opens. If you frequently use a program, it appears on the left column of the Start menu for easy access. When a program, such as WordPad, appears on the Start menu with an arrow, the submenu displays a list of recently opened files for the program known as a **jump list** for easy access. If the program you want to start doesn't appear in the frequently used list, you can use the Search box at the bottom of the Start menu, or you can use the All Programs submenu to locate and start it.

### 2. Point to **All Programs** on the Start menu

The All Programs submenu opens, listing the programs and subfolders for programs installed on your computer. WordPad is in the folder called Accessories.


### 3. Click **Accessories** on the All Programs submenu

The Accessories folder list opens, as shown in Figure B-1. The Accessories folder contains several programs to help you complete common tasks. The All Programs submenu remains open and displays the Back command at the bottom.

### 4. Point to **Back** on the All Programs submenu

The Start menu reappears, displaying the recently used programs in Windows 7.

### 5. Click **All Programs** on the Start menu, then click **WordPad** on the All Programs submenu under Accessories

Your mouse pointer changes momentarily to , indicating that Windows is starting the WordPad program. The WordPad window then opens on your screen.

### 6. Click the **Maximize button** in the upper-right corner of the WordPad window, if necessary



The WordPad window expands to fill the screen, as shown in Figure B-2. The WordPad window includes a title bar at the top with the filename (currently untitled with the name "Document") and program name, a customizable toolbar, called the **Quick Access toolbar**, the **WordPad button** to select file-related commands, a **Ribbon** with two tabs—Home and View—to quickly select document-related commands, as well as the ruler, the work area, and the status bar. A blinking line, known as the **insertion point**, appears in the work area of the WordPad window, indicating where new text will appear. A button, called a taskbar button, appears on the taskbar. **Taskbar buttons** represent open windows on the desktop. In the next lesson, you open and save a document in WordPad.

#### QUICK TIP

If a scroll bar appears on the right side of the All Programs submenu, scroll up or down the menu to view more elements.

#### TROUBLE

If the ruler or status bar does not appear, click the View tab on the Ribbon, then click the element you want to activate so that a check mark appears.


**FIGURE B-1:** Starting WordPad using the Start menu**FIGURE B-2:** Windows desktop with the WordPad window open

## Creating documents in other languages

You can install multiple languages on your computer, such as Hebrew, Arabic, Japanese, French, Spanish, German, and many others. You can choose which language you want to use when you create a document, then Windows makes the characters for that language available. To install additional languages, click the Start button, click Control Panel, then click Change keyboards or other input methods (under Clock, Language, and Region) to open the Region and Language dialog box. Click Change keyboards to open the Text Services and Input Languages dialog box with the General tab on top, then click Add to open the Add Input Language dialog box. The languages you can add appear in a list. Scroll down the list, click the plus sign next to the language you want to add, click the plus sign next to Keyboard or Speech, then click the check box next to the language element you

want to add. If you have more than one language installed, the Language bar allows you to select the language you want to use. To set Language bar settings, click the Language Bar tab in the Text Services and Input Languages dialog box, and then click the option to display the Language bar, either Docked in the taskbar or Floating On Desktop. The Language bar will not appear unless you have more than one language installed. To compose a document that uses more than one language, click the Input language button on the Language bar, click the language you want to use in the list that opens, then type your message. The language setting remains in place until you change it or shut down your computer. Any recipient of multilanguage documents must also have the same languages installed on their computer to read and edit the documents.

# Opening and Saving a WordPad Document

A **document** is a file you create using a word-processing program, such as a letter, memo, or resume. When you start WordPad, a blank document opens which is known as the **document window**. You can enter information to create a new document and save the result in a file, or you can open an existing file and save the document with changes. Until you save a document, it is stored in the computer's **random access memory (RAM)**, temporary storage whose contents are erased when you turn off the computer. To store a document permanently, you save it as a file. The first time you save a file, you need to specify a filename and folder in the Save As dialog box. The next time you save, the program saves the file with the same name in the same folder. If you want to change a file's name or location, you can use the Save As dialog box again to create a copy of the original file.  You have been brainstorming some new tour ideas. Rather than typing the information from scratch, you open an existing document. You want to preserve the original tour ideas so you save it with a new name before making changes to it.

## STEPS

### QUICK TIP

To quickly open a recently used file, point to the WordPad button, then click a file in the right column of the menu.

### TROUBLE

In this book, files are displayed with file extensions. Your display might differ.

### TROUBLE

If there aren't any filenames in the file list, click the Files of type list arrow, then click Rich Text Format (\*.rtf).

1. Click the **WordPad button** , then click **Open**

The Open dialog box opens. You use the Open dialog box to locate and choose the file you want to open. The **Navigation pane**, located on the left side of the dialog box, is used to navigate to common locations and recently used files and folders. The **Address bar** at the top of the dialog box indicates the current folder location. The folder location, which appears as a series of links separated by arrows, creates a **path** from the drive to the folder. You select a location by clicking a drive or folder location name in the Address bar, or by clicking a link arrow to the right of the location to select a subfolder location.

2. Click **Computer** in the Navigation pane, or click the leftmost link arrow in the Address bar and click **Computer**, then, in the window, double-click the drive and folder where you store your Data Files

A list of files and folders appears in the file list, as shown in Figure B-3. The files shown are determined by the option chosen in the Files type list. The Files type list box indicates that the documents shown in this list are in the All Wordpad Documents (.rtf), the default format for WordPad files. **Rich Text Format (RTF)** is a file format that includes formatting for text files and can be opened and read by many other programs.

3. In the list of files, click **WIN B-1.rtf**, then click **Open**

The WIN B-1.rtf file is a document that contains your tour package ideas. The only way to prevent accidental changes from occurring to an original document is to save it in another file with a new name.

4. Click the **WordPad button** , point to **Save as**, click **Rich Text document**, then click **Browse Folders**, if necessary, to expand the dialog box

The Save As dialog box opens, as shown in Figure B-4. You use the Save As dialog box to save an existing document with a new name and in a different folder or drive. The Save as submenu allows you to select a file format for the new document. In addition to RTF, you can also save documents in **Office Open XML Document (DOCX)**, which is for Microsoft Word 2007, **OpenDocument Text (ODT)**, which is for exchanging Office documents, and **Text Document (TXT)**, which is for plain text.


5. Type **Tour Ideas** in the File name text box

As soon as you start typing, the text you type replaces the selected text in the File name text box. When you type a name in the File name text box, **AutoComplete** suggests possible matches with previous filename entries. You can continue to type or click the File name list arrow, then click the correct filename from the list.


6. Click **Save**

The file is saved as Tour Ideas.rtf in the same folder and drive as the WIN B-1.rtf file.

**FIGURE B-3: Open dialog box**



**FIGURE B-4: Save As dialog box**




**Working with filename extensions**

The program Windows uses to open a document depends on a three- or four-letter extension to the document’s filename, called a **filename extension**. You might have never seen a document’s filename extension because your system might be set up to hide it. The filename extension for simple text files is “.txt” (pronounced “dot t-x-t”), and many graphic filenames have the extension “.bmp.” This means that the full name for a text file named Memo is Memo.txt. If you double-click a document whose filename ends with the three-letter extension “.txt,” Windows automatically opens the document with Notepad, a text-only editor. If you want to display or change filename extension settings, open the Control Panel,

click Appearance and Personalization, then click Folder Options. If you want to display filename extensions in dialog boxes and windows, click the View tab in the Folder Options dialog box, then click the Hide extensions for known file types check box to deselect it in the Advanced settings list box. If you want to change the program Windows automatically starts with a given filename extension, right-click the file that you want to change, point to Open with, click Choose default program, then click the program you want to use to open this file. If you want all files of that type to open with the same program, select the Always use the selected program to open this kind of file check box, then click OK.

# Modifying Text in WordPad

When you use a word-processing program, you can **edit**, or change, the contents of the document without re-creating it. You can move text from one place to another using the Cut and Paste commands or the **drag-and-drop** method, which allows you simply to drag text from one location to another. When selected text is cut from a document, Windows removes it from the document and places it on the **Clipboard**, a temporary storage place where it remains available to be pasted elsewhere. You can also change the **format**, or the appearance, of the text and graphics in a document so that the document is easier to read or more attractive. For special emphasis, you can combine formats, such as bold and italic. In addition, you can change the font style and size. A **font** is a set of characters with the same typeface or design, such as Arial or Times New Roman, that you can increase or decrease in size. Font size is measured in points; one **point** is 1/72 of an inch high.  You want to add an introduction and modify and move text in the Tour Ideas document, then make the document more attractive.




## STEPS

1. Press [**↓**] three times to place the insertion point in the fourth line, type **Quest Specialty Travel (QST) takes the toil out of travel and puts the thrill back in! Each tour includes adventure, culture, and education (ACE).**, then press [**Enter**]

WordPad keeps the text on multiple lines together in the same paragraph, using a process called **word wrap**. The text wraps to the edge of the window or to the right margin of the ruler depending on your word-wrap settings. When you press [**Enter**], you create a new paragraph. To correct a mistake or to change text, press [**Backspace**] to delete the character to the left of the insertion point until you delete the text, then retype the text.

2. Move the pointer in the margin to the left of “Live your dreams with Quest Specialty Travell,” so that the pointer changes to , then click


When the pointer is in the left margin, clicking selects the entire line. Table B-1 describes several methods for selecting text in a document.

3. Click the **Cut** button  on the Home tab on the Ribbon, click  after the space after the word “world.” in the last sentence, then click the **Paste** button  on the Home tab

The text you selected in Step 2 is cut from the document, placed on the Clipboard, and is now pasted at the location of the insertion point.

4. Double-click the word **French** in the fourth item in the bulleted list to select the entire word, then click the selection and drag it to the left of the word “farm”

As you drag the pointer, a vertical line next to the pointer indicates where the selection will be placed.

5. Position  to the left of the first character in the line “Quest Specialty Travel” at the top of the document, then click and drag to the end of the line




The text you dragged over is selected.

6. Click the **Center** button , the **Bold** button , and the **Italic** button  on the Home tab

The title is now centered and in bold and italic. Note that the Center button is selected (“turned on”), and the Align Left button is deselected (“turned off”). Related buttons on a toolbar, such as Align text left, Center, and Align text right, act like options in a dialog box—click one to turn it on, and the other related ones turn off. Some buttons, such as Bold, Italic, Underline, and Start a list, act as **toggle** switches—click once to turn the format feature on, click again to turn it off.


7. Click the **Undo** button  on the Quick Access toolbar

Italics are removed from the selected text. The **Undo** command reverses the last change made.


8. Click the **Font list arrow**  on the Home tab, scroll down the font list, click **Times New Roman**, click the **Font Size list arrow**  on the Home tab, click **18**, then click the **Save** button  on the Quick Access toolbar

The size of the selected text changes to 18-point Times New Roman, as shown in Figure B-5.

### QUICK TIP

When the pointer is positioned in the WordPad work area, it changes to , which you can click to reposition the insertion point.

### QUICK TIP

To change text color, select the text, click the Text color button  on the Home tab, then select a color.

### QUICK TIP


To add buttons to the Quick Access toolbar, click the Customize Quick Access Toolbar button  on the Quick Access toolbar, then click a button to select it.

FIGURE B-5: Editing and formatting a WordPad document









TABLE B-1: Methods for selecting text


| to select              | do this   |
|------------------------|---|
| A single word          | Double-click the word   |
| A single line          | Click the left margin to the left of the first character in the line  |
| A single paragraph     | Triple-click a word within the paragraph or double-click in the margin to the left of the paragraph                                 |
| Any part of a document | Drag the pointer over the text you want to select   |
| A large selection      | Click at the beginning of the text you want to select, press and hold [Shift], then click at the end of the text you want to select |
| The entire document    | Triple-click in the left margin, press [Ctrl][A], or click the Select all button on the Home tab                                    |

## Setting paragraph tabs and indents

Tabs set how text or numerical data aligns in a document. A **tab stop** is a predefined stopping point along the document's typing line. Default tab stops are set every half-inch on the ruler, but you can set multiple tabs per paragraph at any location. Each paragraph contains its own set of tab stops. The default tab stops appear as small hash marks below the ruler, and the manual tab stops appear as dark marks on the ruler itself. To display the tab stops for a paragraph on the ruler, click any word in the paragraph. To set a tab stop, click the ruler where you want to set it. Once you place a tab stop, you can drag the tab stop to position it where you want. To delete a tab stop, drag it off the ruler. If you want to add or adjust tab stops in multiple paragraphs, simply select the paragraphs first. When you indent a paragraph, you move its edge in from the left or right margin. You can indent the entire left or right edge of a paragraph or just the first line. The markers on the ruler

control the indentation of the current paragraph. The left side of the ruler has three markers. The top triangle, called the **first-line indent marker** , controls where the first line of the paragraph begins. The bottom triangle, called the **hanging indent marker** , controls where the remaining lines of the paragraph begin. The small square under the bottom triangle, called the **left indent marker** , allows you to move the first-line indent marker and the left indent marker simultaneously. When you move the left indent marker, the distance between the hanging indent and the first-line indent remains the same. The triangle on the right side of the ruler, called the **right indent marker** , controls where the right edge of the paragraph ends. You can also click the Paragraph button  on the Home tab to open the Paragraph dialog box and manually set paragraph indents.

# Working with a Graphic in Paint

**Paint** is a Windows accessory you can use to create and work with graphics or pictures. You can open and save pictures created in, or for, other graphics programs and the Internet using several common file formats, such as .bmp, .tiff, .png, .gif, or .jpeg. A **bitmap** file is a map of a picture created from small dots, or pixels. The value of each dot is stored in one or more bits. One bit is used to represent a dot in black and white, or monochrome graphics, whereas multiple bits are used to represent a dot in graphics with color or shades of gray. With a 4-bit graphic, you can use 16 unique colors, an 8-bit graphic 256 colors, and a 24-bit graphic 16 million colors. To draw or modify graphics in Paint, you use buttons, including those in the Tools and Shapes groups, on the Home tab on the Ribbon, and described in Table B-2. The Colors group on the Home tab allows you to select the colors you want to use in Paint. You can open more than one Windows program at a time, called **multitasking**, so while WordPad is still running, you can open Paint and work on drawings and pictures.  You decide you want to include the Quest logo in the Tour Ideas document you created. However, you need to modify it before you can insert the logo.

## STEPS

1. Click the **Start button**  on the taskbar, point to **All Programs**, click **Accessories**, click **Paint**, then click the **Maximize button**  in the Paint window, if necessary


The Paint window opens and is maximized in front of the WordPad window. The Paint window includes a title bar at the top with the filename (currently “Untitled”) and program name, a customizable toolbar called the **Quick Access toolbar**, the **Paint button** used to select file-related commands, and a Ribbon with two tabs—Home and View—to quickly select document-related commands. In addition, the Paint window contains the status bar and the canvas area. The **canvas area**, or **work area**, is the white drawing area within the Paint window that doesn’t include the gray area.

2. Click the **Paint button** , then click **Open**


The Open dialog box opens with all the picture files in the selected folder listed.


3. Navigate to the drive and folder where you store your Data Files, click **WIN B-2.bmp** in the file list, then click **Open**

The file named WIN B-2.bmp, which is a logo, opens in the Paint window, as shown in Figure B-6.

4. Click the **Paint button** , click **Save as**, then save the file as **QST Logo.bmp** to the drive and folder where you store your Data Files


As you type the new name of the file, Windows automatically determines the file type and changes the format in the Save as type list. In this case, the format changes to 24-bit Bitmap.

5. Click the **Magnifier tool**  on the Home tab, then click the canvas area

Notice that the pointer changed to  when you positioned it over the canvas area. The image magnifies to display the logo larger. A tool remains turned on until another tool is selected.

6. Click the **Fill with color tool**  on the Home tab, click **Color 1** on the Home tab if necessary, click the fourth small square from the left in the first row of the Color Box, then move the pointer into the canvas area

The pointer changes to . Color 1 indicates the foreground color and Color 2 indicates the background color. If you want to change the background color, click Color 2 instead of Color 1 before you select a color.

7. Position  so that the pour tip of the icon is in the right unfilled section of the top part of the compass, then click

The closed area you clicked filled with red, the current foreground color. See Figure B-7.

8. Click the **Save button**  on the Quick Access toolbar

Now you can use the recolored logo in other documents.

### QUICK TIP

To change the file format, click the Save as type list arrow, select the format you want, then click Save.

### QUICK TIP


To resize the canvas, drag the white resize handle in the lower-right corner of the canvas.

### QUICK TIP


To set a picture as your desktop background, click the Paint button, point to Set as desktop background, then click an option.



**FIGURE B-6: Company logo in Paint**




**FIGURE B-7: Company logo with a new color fill**



**TABLE B-2: Tools on the Home tab**

| tool                  | used to   | tool                | used to  |
|-----------------------|---|---------------------|--|
| Paste                 | Paste Clipboard or file to the canvas                 | Eraser/Color Eraser | Erase or color part of a drawing                                   |
| Cut                   | Remove selection to the Clipboard                     | Color picker        | Pick up a color from the picture for drawing                       |
| Copy                  | Copy selection to the Clipboard                       | Magnifier           | Magnify part of an image   |
| Crop                  | Remove contents outside selection                     | Brush               | Draw a brush stroke using a brush with the selected size and shape |
| Resize                | Resize or skew selection                              | Shapes              | Draw a shape   |
| Rotate                | Rotate or flip selection                              | Shape outline       | Draw a shape with an outline color or brush                        |
| Rectangular selection | Select a square or rectangular shape                  | Shape fill          | Draw a shape with a fill color or brush                            |
| Free-form selection   | Select a free-form or irregular shape                 | Size                | Draw a shape with a line thickness                                 |
| Pencil                | Draw a freehand line                                  | Color 1             | Select a foreground color  |
| Fill with color       | Fill a closed shape with the current color or texture | Color 2             | Select a background color  |
| Text                  | Enter text in drawings                                | Edit colors         | Change the selected color  |

# Copying Data Between Programs

One of the most useful features Windows offers is the ability to use data created in one file in another file, even if the files were created in different Windows programs. To work with more than one program or file at a time, you simply need to open both of them. To switch from one open window to another, click the correct taskbar button. If you **tile**, or arrange open windows on the desktop so that they are visible, you can switch among them simply by clicking in the window in which you want to work. You can use the Cut, Copy, and Paste commands to move and copy data between different files.  You want to add the company logo, which you modified in Paint, to the Tour Ideas document containing your ideas for travel packages.


## STEPS


### TROUBLE

If your windows aren't tiled, click the taskbar buttons and ensure that both windows are maximized, then repeat Step 1.

### TROUBLE

If you have trouble selecting the logo, click the Zoom in button on the status bar to display 100%, then repeat Step 3.


1. Place the mouse pointer on an empty area of the taskbar, right-click, then click **Show windows side by side** on the shortcut menu  
The windows (Paint and WordPad) are tiled next to one another vertically, so you can maneuver quickly between them while working. Neither window is active at the moment.
2. Click the **QST Logo.bmp – Paint taskbar button** on the taskbar  
Clicking a taskbar button makes the window associated with that button the **active window**, so the Paint program window becomes the active window.
3. Click the **Image button** on the Home tab if necessary, click the **Select tool button arrow**  on the Home tab, click **Rectangular selection**, position the cursor in the upper-left corner of the canvas, click, then drag around the QST logo to select it  
Dragging with the Select tool selects an object in Paint for cutting, copying, or performing other modifications.
4. Click the **Clipboard button** on the Home tab, then click the **Copy button**   
A copy of the logo is placed on the Clipboard, but it also remains in its original place in the file.
5. Click anywhere in the WordPad window to make it active, then click at the top of the WordPad document, above the first line of text  
Clicking in an inactive window is another way to make that window active. The WordPad program becomes active, and the insertion point is blinking near the left margin in the first line on the Tour Ideas document page, where you want the logo to appear.
6. Click the **Clipboard button** on the Home tab, if necessary, click the **Paste button**  in the WordPad window, then click the logo to select it  
The logo is pasted into the document. A selection rectangle with resize handles, as shown in Figure B-8.
7. Click the **Maximize button**  in the WordPad window, click the **Center button**  on the Home tab, then click a blank area of the document window, if necessary  
The logo is deselected, and is now centered horizontally on the page.
8. Click the **Save button**  on the Quick Access toolbar in the WordPad window  
You're finished working with Paint. To close a program and any of its currently open files, click Exit on the Paint menu or click the Close button in the upper-right corner of the program window.
9. Click the **QST Logo.bmp – Paint taskbar button** on the taskbar, click the **Save button** , then click the **Close button**  in the Paint window

**FIGURE B-8:** Logo copied from one program to another

## Switching between files


When you open many file and program windows, the taskbar groups windows from the same program together in one taskbar button to reduce the clutter on the taskbar and save space. For example, if you have five windows open, and two of them are WordPad files, the two WordPad files are grouped together on the taskbar within the one button named *WordPad*. When you click the *WordPad* button on

the taskbar, a thumbnail appears for each open WordPad file, from which you can choose the file you want to view, as shown in Figure B-9. You can point to the thumbnail to temporarily view it or click the thumbnail to switch to it. (To open more than one WordPad window, you need to start two versions of the program using the Start menu.)

**FIGURE B-9:** WordPad taskbar buttons grouped on taskbar


# Embedding or Linking an Object

**Object Linking and Embedding (OLE)** is a way to share information—an object—between two programs. An **object** can be a picture from a graphics program, a chart from a spreadsheet program, a video clip, text, or almost anything else you can create on a computer. The program that creates the object is the **source program**; the program that creates the file into which you want to insert the object is the **destination program**. Likewise, the file that originally contained the object is called the **source file**, and the file where you want to insert the object is called the **destination file**. With **embedding**, a copy of the object becomes part of the destination file, which also increases the size of the file. If you want to edit the object, you make changes in the destination file using the source program, and the original file remains intact. With **linking**, a representation of the object appears in the destination file, but the object is actually stored in the source file. Because a linked object is not stored in the destination file, the object doesn't increase the size of the destination file. If you want to edit the linked object, you make changes in the source file, and the changes will be reflected in the other file the next time you open or update it.

 The company logo is not final yet, so you want to link the source file to the document. Then, you can quickly update the document once the logo is finalized.

## STEPS

### QUICK TIP



To create a new object from Paint, click the Paint drawing button  on the Home tab, draw the image you want, click the Paint button , then click Exit and return to document. Double-click the object to edit it.

### QUICK TIP


When you open a destination file with a linked object, the destination program checks the source file location to reestablish the link. If it doesn't find the file, it displays an alert, asking you to locate it and reestablish the link.

### TROUBLE


If your circle doesn't match Figure B-12, use the Undo button on the Quick Access toolbar, then repeat Step 8.

1. In the WordPad document, click the **QST logo image** to select it, then press **[Delete]**  
The nonlinked logo is now deleted from the Tour Ideas document.
2. Click the **Insert object button**  on the Home tab to open the Insert Object dialog box, then click the **Create from File option button**
3. Click **Browse** to open the Browse dialog box, navigate to the drive and folder where you store your Data Files, click **QST Logo.bmp**, then click **Open**  
The file you selected is listed in the Insert Object File text box. So far, you have completed the same steps to insert a new version of the logo as a linked file that you would have done if you planned to embed the object.
4. Click the **Link check box** to select it, as shown in Figure B-10, then click **OK**  
The two files are now linked. The linked object—the QST logo—remains outlined on the WordPad page.
5. **Right-click the QST logo image, then click Links**  
The Links dialog box opens, as shown in Figure B-11. The box lists the linked objects in the document; in this case, it contains just one—the logo.
6. Click the **Manual option button**, then click **Close**  
The Links dialog box closes. Now the linked logo will be updated only when you choose to do so.
7. **Double-click the QST logo image in WordPad**  
The QST Logo.bmp file is opened in Paint, and the Paint window becomes the active window.
8. **Maximize the Paint window, click the Oval tool**  in the Shapes Box, select the second color in the second row in the Colors Box, drag to draw a circle around the logo, then save the image and close Paint
9. **Right-click the QST logo image, then click Links, click Update Now, click Close, then save your changes and deselect the logo**  
WordPad updates the QST logo from the Paint file. See Figure B-12.


**FIGURE B-10: Insert Object dialog box**



**FIGURE B-11: Links dialog box**



**FIGURE B-12: WordPad document with updated linked object**




**Finding, changing, and breaking a linked object**


Instead of opening the source file to make changes to a linked object, you can open a linked object from within the destination file using the Open Source button in the Links dialog box. The Open Source button finds the source file containing the linked object and opens that file. The Links dialog box keeps track of the source file location. You can change the source file to a different file or location by using the Change Source button. If you want to disregard a link and change

it to an embedded object, right-click the linked object in the destination file, click Object properties to open the Linked Bitmap Image Properties dialog box, click the Link tab, click Break Link, click Yes in the message box, then click OK. On the Link tab in the Linked Bitmap Image Properties dialog box, you can also open or change the source file, change update options, and update the source for the selected object.

# Printing a Document

**Printing** a document creates a **printout** or **hard copy**, a paper document that you can share with others or review as a work in progress. Most Windows programs have print options that you can set using a Print dialog box. Although printing options vary from program to program, the process works similarly in most of them. Typically, you can access the Print dialog box using a Print command on a menu. If you want to use the current print options and bypass the Print dialog box, you can use the Quick Print command on the Print submenu. It is a good idea to use the **Print Preview** feature to look at the layout and formatting of a document before you print it. You might catch a mistake, find that the document fits on more pages than you wanted, or notice formatting that you want to do differently. Making changes before you print saves paper.  You decide to preview the Tour Ideas document to ensure you are satisfied with how it looks before printing it. When satisfied with the result, you print the Tour Ideas document.

## STEPS

1. In the WordPad window, add your name to the bottom of the document, click the **WordPad button** , point to **Print**, then click **Print preview**

The Print preview window opens and a reduced but proportionate image of the page appears in the Print preview window, as shown in Figure B-13.

2. Move the pointer over the logo so that the pointer changes to , then click the screen

The preview image of the page zooms in to appear larger. Note the size of the **margin**, which is the space between the text and the edge of the document.

3. Click the **Page setup button**  on the **Print preview tab**

The Page Setup dialog box opens. In this dialog box, you can change the margin setting to decrease or increase the area outside the dotted rectangle. You can also change other printing options, including the paper size and page orientation. Page **orientation** describes the direction text is printed on the page. When the page is taller than it is wide, its orientation is **portrait**; when the page is wider than it is tall, its orientation is **landscape**.

4. If necessary, drag to select the number in the Left text box, type **1**, select the number in the Right text box, type **1**, then click **OK**

The document appears in the Print preview window with the smaller page margins.

5. Click the **Print button**  on the **Print preview tab**

The Print dialog box opens, as shown in Figure B-14, showing various options available for printing.

6. Select the printer you want to use if necessary, then click **Print**

The Tour Ideas document prints. While a document prints, a printer icon appears in the notification area of the taskbar that you can point to in order to get status information. The Print preview window closes, and you return to the Tour Ideas document.

7. Click the **Save button** , then click the **Close button**  in the WordPad window

WordPad saves your changes in the documents and the program closes.


### QUICK TIP

To print a document with the default settings in the Print dialog box, click the WordPad button, point to Print, then click Quick print.


### TROUBLE

If a printer is not available, double-click the Add Printer icon and answer a series of questions using the Add Printer Wizard to install one.

**FIGURE B-13: WordPad document in Print Preview**



**FIGURE B-14: Print dialog box**




### Creating an XPS document

**XML Paper Specification (XPS)** is a secure fixed-layout format—similar to an Adobe PDF file—developed by Microsoft that retains the format you intended on a monitor or printer. An XPS document is useful when you want to create a document primarily intended to be read and printed, not modified. Windows 7 allows you to save a document as an XPS file, which you can send to others for review

in an e-mail. To create an XPS file, select the Microsoft XPS Document Writer in the Print dialog box instead of a printer, click Print, specify a filename and location, then click Save. To view an XPS file, you need to have a viewer—free downloadable software from Microsoft Office Online—installed on your computer.

# Playing a Video or Audio Clip

Windows 7 comes with a built-in accessory called **Windows Media Player**, which you can use to play video, audio, and mixed-media files, known as **clips**, stored on your computer, a CD, a DVD, a local network, or the Internet. You can also copy, or **rip**, individual music tracks or entire CDs to your computer and create your own jukebox or playlist of media. In addition, you can create, or **burn**, your own audio CDs or data DVDs, and copy music and videos to portable digital audio players and PCs, such as an MP3 player, cell phone, or mobile device. You can also access online stores to purchase music and other media. With Windows Media Player, you can modify the media, control the settings, and change the player's appearance, or **skin**. Windows 7 comes with Windows Media Player version 12; however, new versions are periodically released. To check online for the most recent version of Windows Media Player, right-click the taskbar in Windows Media Player, point to Help, then click Check for updates.  You want to learn how to use Windows Media Player to play travel video and audio clips for customers.

## STEPS

### TROUBLE

If a dialog box opens asking you to choose Recommended settings or Custom settings, click the option you prefer, then click Finish. If you are working in a lab, ask your instructor or technical support person for help.

### QUICK TIP

To play an audio track from the Library, double-click the track you want to play.

### QUICK TIP

To play a music CD, insert the CD in the disc drive and wait for Windows Media Player to start playing the CD.

1. Click the **Windows Media Player button**  on the taskbar, then click the **Maximize button**  in the Windows Media Player window, if necessary

The Windows Media Player window opens. A taskbar with tabs is at the top of the window and player controls that look and function similarly to those on a CD or DVD player are along the bottom. The Library window opens by default, as shown in Figure B-15, displaying the media you currently have stored on your computer.

2. Right-click a blank area of the Windows Media taskbar, point to **File** on the menu, click **Open**, navigate to the drive and folder where you store your Data Files, click **WIN B-3.wmv**, then click **Open**

A video clip of wildflowers appears in the Now Playing window, a smaller more compact window, as shown in Figure B-16. The video clip plays once.

3. Click the **Switch to Library button**  in the upper-right corner of the Now Playing window

The Library window opens in Windows Media Player.

4. Right-click a blank area of the Windows Media taskbar, point to **File** on the menu, click **Open**, navigate to the drive and folder where you store your Data Files, if necessary, click **WIN B-4.wma**, then click **Open**

The video clip is closed and the audio clip plays once. You can play the media clip continuously, or **loop**.

5. Click the **Turn repeat on button**  at the bottom of the Media Player to turn on the option, then click the **Switch to Now Playing button**  at the bottom of the Media Player window

The Now Playing window opens. When you play audio in the Now Playing window, you can display a **visualization** (a visual effect), which displays color and shapes that change with the beat of the sound.

6. Right-click a blank area of the window, point to **Visualizations**, point to **Battery**, then click **eletriarnation**

The visual effect continuously displays while the audio plays. The Play tab from the Library window can be accessed from the Now Playing window as well.

7. Right-click a blank area of the window, then click **Show list**

The Play tab from the Library window opens in the Now Playing window.


8. After the audio repeats several times, click the **Stop button**  at the bottom of the Windows Media Player window

You can control the playback of media in the Now Playing window.

9. Right-click a blank area of the window, then click **Hide list**, click the **Switch to Library button** , click the **Turn repeat off button**  to turn off the option, then click the **Close button**  in the Windows Media Player window



**FIGURE B-15: Library window in Windows Media Player**



**FIGURE B-16: Playing a video clip in the Now Playing window**




### Playing media from other computers or the Internet

You can use Windows Media Player to play media available on the Internet or from other networked computers, such as videos, live broadcasts, and music tracks. You can stream the media directly from another computer on your network or over the Internet or from a Web site, or you can download the media file to your computer. Delivering high-quality, continuous video, live broadcasts, sound, and music playback is known as **streaming media**. When you stream the media, the video or music starts playing while the file is transmitted to you from another networked computer or over the Internet. The streaming media is not stored on your computer. If you have media on another computer over a network, HomeGroup (a home-sharing network), or the Internet, you can use commands on the Stream menu to allow access and control of the media on your computer. You can access the streaming media from

the Navigation pane just your like local media. You can also use the Media Guide button in the Windows Media Player to help you find media—music, movies, and radio—on the Internet. To stream media from the Internet, locate the Web site that contains the media you want to play, click the link to the media, then wait for Windows Media Player to start (if necessary) and the first data bits to be transmitted to a temporary memory storage area called a **buffer** and for the media to start playing automatically. The buffer continues to download the media until it's done as Windows Media Player plays the media in the buffer. When you download a media file, you wait for the entire file to be transferred to your computer. To download a file, use a Web browser to locate the media you want to download from the Internet, then click the download link to download and save it locally.

# Working with Windows Media

If you have Windows Home Premium, Professional, or Ultimate edition you can use Windows Media Center to play and work with media. Windows Media Center is an entertainment system integrated into your computer that lets you watch live or recorded TV or Netflix movies, play video and look at pictures, listen to music and radio using an FM tuner or the Internet, play and burn CDs and DVDs, browse online media, and play games. Windows Media Center is designed with a display and navigation unlike other Windows programs. When you start Windows Media Center, the program window fills the entire screen and no menus or toolbars are displayed. You navigate by scrolling through a list of main categories, and then scrolling through commands for the selected category. Play, Record, and other VCR/DVD type commands are available when you move the pointer to display them. In addition to the pointer, you can use a remote control or a touch screen to navigate the system and play the media you want. To play FM radio or watch TV, you need to have an FM tuner and a TV tuner card installed on your computer.  After creating a DVD for the latest marketing promotion, you want to use Windows Media Center to play it.

## STEPS

### TROUBLE

If you're asked to set up Windows Media Center, click Continue, choose Express Setup, and follow the on-screen instructions.

### QUICK TIP


If you prefer a desktop view, you can use Windows Media Center as a desktop gadget.


### QUICK TIP

To play music, click Home button, click the Music category, click music library, scroll left or right, select an album, select a track, then click play song.


### TROUBLE

If you're asked to add more videos to Media Libraries, click Cancel.

1. Click the **Start button**  on the taskbar, point to **All Programs**, then click **Windows Media Center**

The Windows Media Center window opens with its categories listed. When you move your mouse, the Home button moves to the upper-left corner along with the Back button. The Home button brings you back to the main menu screen. The lower-right corner displays VCR and TV tuner controls.
2. Click the **Maximize button**  if necessary, point to the list in the middle of the start screen, then move the pointer to the top or bottom edge of the screen above or below the list to display an arrow and scroll the list


You can click the up or down arrow to scroll categories one at a time.
3. Click the up or down arrow to scroll to the **Tasks category**, as shown in Figure B-17, click the **settings command**, then click the **Media Libraries command**

The settings command allows you to customize Windows Media Center and add media libraries.
4. Click the **Videos option**, click **Next**, click the **Add folders to the library option**, click **Next**, click the destination option where you store your Data Files, click **Next**, navigate to the drive and folder where you store your Data Files, select the **UnitB check box**, click **Next**, click the **Yes, use these locations option**, click **Finish**, then click the **Back button** 

The media files in the UnitB folder are added to their respective libraries, available for use. The Windows Media Center Home screen window opens.
5. Press **[Up Arrow]** or **[Down Arrow]** to scroll to the **Pictures + Videos category**

The category is selected with the picture library, play favorites, and video library commands displayed.
6. Click the **video library command**

The video library category is now active. The Data Files from UnitB are cataloged in the video library.
7. Click **<folders>** at the top of the video library category screen, if necessary, click **UnitB**, point to **WIN B-5**, then click the thumbnail

After a moment, the video plays, as shown in Figure B-18. If the playback and navigation controls autohide, move the mouse to display them again.
8. Move the pointer to display the controls, then click the **Home button** 


The Windows Media Center Home screen window reopens. If the video has not completed playing, the Home screen controls display with the video playing in the background.
9. Click the **Close button**  in the Windows Media Center window

FIGURE B-17: Navigating in Windows Media Center




FIGURE B-18: Playing a video in Windows Media Center



### Changing Windows Media Center settings

You can set up and customize Windows Media Center by selecting the Tasks category on the Home screen, and then selecting the settings command. You can set general options for Windows Media Center and specific options for each of the media types, including TV, Pictures, Music, and DVD. You can also set options for extenders and libraries. A Windows Media Center Extender is a device you connect to your computer, such as a TV, DVD player, digital camera, or Xbox 360.

When you connect an extender, you can control the device from Windows Media Center within a networked environment. Before you get started with Windows Media Center, it's a good idea to set general options, which include startup and window behavior, visual and sound effects, program library options, Windows Media Center setup, parental controls, automatic download options, optimization, and privacy.